



Specific data is required to help facilitate the configuration of your account. If, at any time, you find yourself needing help to understand the information we are asking for, please don't hesitate to contact Customer Care at customer care@zonarsystems.com or (877) 843-3847.

SYSTEM VARIABLES

Company name:

United States

Canada

TABLET SHELL

Sleep timeout: Driver profile cache limit: Screen off while in motion:

Logout timeout: Show driver name as: True False

ZONAR LOGS

Maximum personal conveyance distance: YES NO

* Canada PC daily limit is 75km/46.6 miles

Key OFF event duty status: OFF ON Selecting "NO" allows a driver to edit their logs with dispatcher approval and selecting "YES" allows a driver to edit their logs without dispatcher approval.

Incidental movement threshold:

Idle automatic duty status: ON DRIVE

United States HOS Ruleset: YES NO

Canada HOS Ruleset:

INITIALS



EVIR

Maximum inspections to retain:

NAV

Allow driver to override asset profile: YES NO
ALK CoPilot uses asset profile for routing. If incorrect information is entered, the route solution provided may include bridges or overpasses incompatible with the actual vehicle dimensions/weight.

MESSAGING

Tablet maximum message retention days: Auto play messages: OFF ON
Allow message to be played when in motion: OFF ON Sync lookback days:

ZONAR COUNT

Show Manual Add Rider: YES NO
Show Manual Delete Rider: YES NO
Enable Dispatcher Alerting: YES NO

AUTHORIZED USERS (MAX 5)

Besides yourself - you can list up to five authorized individuals that can make changes to the account. Only these people will be allowed to make account changes.

Name: Email: Phone Number:

INITIALS

By signing this form, you are: (i) representing that you are authorized to act on behalf of your company, (ii) acknowledging that you have reviewed the information on this document, and (iii) are instructing Zonar to install and configure the Zonar Tablet (and the ZLogs application) as indicated on this form. (iv) You acknowledge that Zonar will hold retain messages for a minimum of 6 months and ZLogs information will be retained for a maximum of 6 months. (v) If any future changes to the account need to be made, only you or one of the authorized users may do so.

***PLEASE NOTE THAT IF ANY MODIFICATIONS ARE MADE TO THE TABLET SHELL OR ZLOGS FIELD AFTER DIGITALLY SIGNING THIS DOCUMENT IT WILL VOID THE FORM AND REQUIRE THE CUSTOMER TO FILL OUT A NEW FORM.**

Name:

Signature: _____

Title:

Date:

Tablet Required Data Form Definitions

Tablet Shell

Sleep Timeout - The threshold of time until the tablet goes to “sleep” or when the screen dims. The operator will still be logged in, and it will just require a pin code to gain access again. Similar to a cell phone when it’s not in use.

Logout Timeout - The maximum amount of time the operator can be logged in. If the tablet is not used or inactive after an x amount of time and is not in a motion status, it will automatically logout the operator for security reasons.

Driver Profile Cache Limit - The number of days that the tablet stores the operator profile. When cache stores the operator profile, it makes logging in faster as the tablet recognizes the operator without having to re-authenticate.

ZLogs

Maximum Personal Conveyance Distance - This setting defines the maximum amount of mileage allowed to be driven while in PC status. Upon reaching the limit, the tablet will force the operator to switch to “Drive” status.

* **Key OFF Even Duty Status** - Determines which duty status will be set when the engine is keyed OFF. Off = Duty status will be changed to “Off Duty”. On = Duty status will be changed to/stay in “On Duty”.

Incidental Movement Threshold - After traveling an x amount of miles/distance and if the operator is not in the “Drive” status, the tablet will automatically switch the operator to the “Drive” status.

* **Idle Automatic Duty Status** - Determines what duty status the tablet will automatically switch when the vehicle is idling. On = Status will be switched to “On-Duty” and Drive = Status will stay at “Drive”.

Canada HOS Ruleset - Hours of Service in Canada.

Allow Driver to Edit Duty Status Logs without Dispatcher Approval - Allows operators to edit logs without the approval of a dispatcher.

EVIR

Maximum Inspection to Retain - The threshold of days that the tablet stores inspections for viewing.

NAV (Navigation)

Allow Driver to Override Asset Profile - A default profile is loaded in the tablet based on what is set on the Admin>Assets> Manage section of Ground Traffic Control. If set to “Yes”, the operator can override those settings.

Messaging

Maximum Message Retention Days - This setting defines how many days the tablet keeps messages on the device. Any messages that has reached the maximum day will be purged.

Allow Messages to be played while in motion - When the vehicle is detected to be in motion and this setting is set to on, it will provide the operator with the option to play/read the message out loud.

Auto Play Messages - When the vehicle is detected to be in motion and this setting is set to on, it will automatically play the message out loud.

Sync Lookback Days - This setting only applies when the operator is logged in to the tablet for the first time. It will define how many days the application will make a sync request for. On a regular login, the app will sync based on the last message received.

Zonar Count

Show Manual Add Rider - Allows operators to manually add a rider.

Show Manual Delete Rider - Allows operators to manually delete a rider.

Enable Dispatcher Alerting - Allows the operator to alert the dispatcher at the end of a session.

Automatic Duty Status will notify the operator that in 30 seconds they will be switched into ON/OFF duty. This notification gives the operator the option to remain in their current status or to manually change duty status* as well.